
mdfreader Documentation

Release 4.0

Aymeric Rateau

Jul 14, 2020

CONTENTS

1	mdfreader module documentation	3
1.1	Platform and python version	3
1.2	Dependencies	3
1.3	mdfreader	3
2	mdf module documentation	13
2.1	Dependencies	13
2.2	mdf	13
3	mdf3reader module documentation	19
3.1	mdf3reader	19
4	mdfinfo3 module documentation	25
4.1	Dependencies	25
4.2	mdfinfo3	25
5	mdf4reader module documentation	27
5.1	Dependencies	27
5.2	mdf4reader	27
6	mdfinfo4 module documentation	35
6.1	mdfinfo4	35
7	channel module documentation	45
8	Indices and tables	53
	Python Module Index	55
	Index	57

Contents:

MDFREADER MODULE DOCUMENTATION

Measured Data Format file reader main module

1.1 Platform and python version

With Unix and Windows for python 2.6+ and 3.2+

Author Aymeric Rateau

Created on Sun Oct 10 12:57:28 2010

1.2 Dependencies

- Python >3.4 <<http://www.python.org>>
- Numpy >1.14 <<http://numpy.scipy.org>>
- Sympy to convert channels with formula
- bitarray for not byte aligned data parsing
- Matplotlib >1.0 <<http://matplotlib.sourceforge.net>>
- scipy for NetCDF
- h5py for the HDF5 export
- xlwt for the excel export (not existing for python3)
- openpyxl >2.0 for the excel 2007 export
- hdf5storage for the Matlab file conversion
- zlib to uncompress data block if needed

1.3 mdfreader

```
class mdfreader.mdfreader.Mdf (file_name=None, channel_list=None, convert_after_read=True,  
                                filter_channel_names=False, no_data_loading=False, compression=False, convert_tables=False, metadata=2)
```

Bases: *mdfreader.mdf4reader.Mdf4, mdfreader.mdf3reader.Mdf3*

Mdf class

fileName
file name

Type str

MDFVersionNumber
mdf file version number

Type int

masterChannelList
Represents data structure: a key per master channel with corresponding value containing a list of channels
One key or master channel represents then a data group having same sampling interval.

Type dict

multiProc
Flag to request channel conversion multi processed for performance improvement. One thread per data group.

Type bool

fileMetadata
file metadata with minimum keys : author, organisation, project, subject, comment, time, date

Type dict

read(*file_name = None, multi_processed = False, channel_list=None, convert_after_read=False, filter_channel_names=False, no_data_loading=False, compression=False*)
reads mdf file version 3.x and 4.x

write (*file_name=None*)
writes simple mdf file

get_channel_data (*channel_name*)
returns channel numpy array

convert_all_channel ()
converts all channel data according to CCBLOCK information

get_channel_unit (*channel_name*)
returns channel unit

plot (*channels*)
Plot channels with Matplotlib

resample (*sampling_time = 0.1, master_channel=None*)
Resamples all data groups

export_to_csv (*file_name = None, sampling = 0.1*)
Exports mdf data into CSV file

export_to_NetCDF (*file_name = None, sampling = None*)
Exports mdf data into netcdf file

export_to_hdf5 (*file_name = None, sampling = None*)
Exports mdf class data structure into hdf5 file

export_to_matlab (*file_name = None*)
Exports mdf class data structure into Matlab file

export_to_excel (*file_name = None*)
Exports mdf data into excel 95 to 2003 file

export_to_xlsx (*file_name=None*)
Exports mdf data into excel 2007 and 2010 file

convert_to_pandas (*sampling=None*)
converts mdf data structure into pandas dataframe(s)

keep_channels (*channel_list*)
keeps only list of channels and removes the other channels

merge_mdf (**mdf_class**):
Merges data of 2 mdf classes

Notes

mdf class is a nested dict. Channel name is the primary dict key of mdf class. At a higher level, each channel includes the following keys :

- 'data' : containing vector of data (numpy)
- 'unit' : unit (string)
- 'master' : master channel of channel (time, crank angle, etc.)
- 'description' : Description of channel
- 'conversion': **mdfinfo nested dict for CCBLOCK**. Exist if channel not converted, used to convert with getChannelData method

Examples

```
>>> import mdfreader
>>> yop=mdfreader.Mdf('NameOfFile')
>>> yop.keys() # list channels names
# list channels grouped by raster or master channel
>>> yop.masterChannelList
>>> yop.plot('channelName') or yop.plot({'channel1','channel2'})
>>> yop.resample(0.1) or yop.resample()
>>> yop.export_to_csv(sampling=0.01)
>>> yop.export_to_NetCDF()
>>> yop.export_to_hdf5()
>>> yop.export_to_matlab()
>>> yop.export_to_excel()
>>> yop.export_to_xlsx()
>>> yop.convert_to_pandas() # converts data groups into pandas dataframes
>>> yop.write() # writes mdf file
# drops all the channels except the one in argument
>>> yop.keep_channels(['channel1','channel2','channel3'])
>>> yop.get_channel_data('channelName') # returns channel numpy array
>>> yop=mdfreader.Mdf() # create an empty Mdf object
# add channel in Mdf object
>>> yop.add_channel(channel_name, data, master_channel, master_type, unit='lumen',
↳ description='what you want')
>>> yop.write('filename') # change version with yop.MDFVersionNumber or
↳ specifically use write3/4()
```

concat_mdf (*mdf_class*)
Concatenate data of input mdf class after the current one.

Parameters **mdf_class** (**Mdf**) – mdf class instance to be concatenated after self

Notes

It creates union of both channel lists and fills with Nan for unknown sections in channels. If one channel is not present in both classes, masked array is created. If invalid bytes are present, masked array are created.

convert_all_channels ()

Converts all channels from raw data to converted data according to CCBlock information. Converted data will take more memory.

convert_to_pandas (*sampling=None*)

converts mdf data structure into pandas dataframe(s)

Parameters **sampling** (*float, optional*) – resampling interval

Notes

One pandas dataframe is converted per data group (one master per data group)

cut (*master_channel, begin=None, end=None*)

Cut data

Parameters

- **master_channel** (*str*) – channel to cut data (can be master channel)
- **begin** (*float*) – beginning value in master channel from which to start cutting in all channels
- **end** (*float*) – ending value in master channel from which to start cutting in all channels

Notes

Only the data groups with same master type as master_channel will be cut (only for mdf4)

export_to_NetCDF (*file_name=None, sampling=None*)

Exports mdf data into netcdf file

Parameters

- **file_name** (*str, optional*) – file name. If no name defined, it will use original mdf name and path
- **sampling** (*float, optional*) – sampling interval

Notes

Dependency: scipy

export_to_csv (*file_name=None, sampling=None*)

Exports mdf data into CSV file

Parameters

- **file_name** (*str, optional*) – file name. If no name defined, it will use original mdf name and path
- **sampling** (*float, optional*) – sampling interval. None by default

Notes

Data saved in CSV file be automatically resampled as it is difficult to save in this format data not sharing same master channel -> not applicable for mdf4 in case there are master channels

with various types

Warning: this can be slow for big data, CSV is text format after all

export_to_excel (*file_name=None*)

Exports mdf data into excel 95 to 2003 file

Parameters **file_name** (*str, optional*) – file name. If no name defined, it will use original mdf name and path

Notes

xlwt is not fast even for small files, consider other binary formats like HDF5 or Matlab. If there are more than 256 channels, data will be saved over different worksheets. Also Excel 2003 is becoming rare these days, prefer using exportToXlsx. Dependencies: xlwt for python 2.6+, xlwt3 for python 3.2+

export_to_hdf5 (*file_name=None, sampling=None, compression=None, compression_opts=None*)

Exports mdf class data structure into hdf5 file

Parameters

- **file_name** (*str, optional*) – file name. If no name defined, it will use original mdf name and path
- **sampling** (*float, optional*) – sampling interval.
- **compression** (*str, optional*) – HDF5 compression algorithm. Valid options are 'gzip', 'lzf'. gzip compression recommended for portability. szip compression not supported due to legal reasons.
- **compression_opts** (*int, optional*) – HDF5 gzip compression level, 0-9. Only valid if gzip compression is used. Level 4 (default) recommended for best balance between compression and time.

Notes

The maximum attributes will be stored. Data structure will be similar has it is in masterChannelList attribute. Dependency: h5py

export_to_matlab (*file_name=None*)

Export mdf data into Matlab file preferrably in format 7.3

Parameters **file_name** (*str, optional*) – file name. If no name defined, it will use original mdf name and path

Notes

This method will dump all data into Matlab file but you will loose below information: - unit and descriptions of channel - data structure, what is corresponding master channel to a channel. Channels might have then different lengths. Dependency: hdf5storage, scipy

export_to_parquet (*file_name=None*)

Exports mdf data into parquet file

Parameters `file_name` (*str*, *optional*) – file name. If no name defined, it will use original mdf name and path with .parquet extension

export_to_xlsx (*file_name=None*)

Exports mdf data into excel 2007 and 2010 file

Parameters `file_name` (*str*, *optional*) – file name. If no name defined, it will use original mdf name and path

Notes

It is recommended to export resampled data for performances Dependency: openpyxl

get_channel_data (*channel_name*, *raw_data=False*)

Return channel numpy array

Parameters

- **channel_name** (*str*) – channel name
- **raw_data** (*bool*) – flag to return non converted data

Returns converted, if not already done, data corresponding to channel name

Return type numpy array

Notes

This method is the safest to get channel data as numpy array from 'data' dict key might contain raw data

keep_channels (*channel_set*)

keeps only a list or set of channels and removes the other channels

Parameters `channel_set` (*list or set of str*) – list or set of channel names

merge_mdf (*mdf_class*)

merge data of input mdf class with the current one.

Parameters `mdf_class` (*Mdf*) – mdf class instance to be merged with self

Notes

If there are common channel names between the 2 mdf, channels are renamed to make them unique

plot (*channel_name_list_of_list*)

Plot channels with Matplotlib

Parameters `channel_name_list_of_list` (*str or list of str or list of list of str*) – channel name or list of channel names or list of list of channel names list of list will create multiplots

Notes

Channel description and unit will be tentatively displayed with axis labels

plot_all ()

read (*file_name=None, multi_processed=False, channel_list=None, convert_after_read=True, filter_channel_names=False, no_data_loading=False, compression=False, metadata=2*)
reads mdf file version 3.x and 4.x

Parameters

- **file_name** (*str, optional*) – file name
- **multi_processed** (*bool*) – flag to activate multiprocessing of channel data conversion.
- **channel_list** (*list of str, optional*) – list of channel names to be read. If you use `channelList`, reading might be much slower but it will save you memory. Can be used to read big files.
- **convert_after_read** (*bool, optional*) – flag to convert channel after read, True by default. If you use `convertAfterRead` by setting it to false, all data from channels will be kept raw, no conversion applied. If many float are stored in file, you can gain from 3 to 4 times memory footprint. To calculate value from channel, you can then use method `getChannelData()`
- **filter_channel_names** (*bool, optional*) – flag to filter long channel names from its module names separated by ‘.’
- **no_data_loading** (*bool, optional*) – Flag to read only file info but no data to have minimum memory use.
- **compression** (*bool or str, optional*) – To compress data in memory using `blosc` or `bcolz`, takes cpu time. if `compression = int(1 to 9)`, uses `bcolz` for compression. if `compression = ‘blosc’`, uses `blosc` for compression. Choice given, efficiency depends of data.
- **metadata** (*int, optional, default = 2*) – Reading metadata has impact on performance, especially for mdf 4.x using xml. 2: minimal metadata reading (mostly channel blocks). 1: used for `noDataLoading`. 0: all metadata reading, including Source Information, Attachment, etc..

Notes

If you keep `convertAfterRead` to true, you can set attribute `mdf.multiProc` to activate channel conversion in multiprocessing. Gain in reading time can be around 30% if file is big and using a lot of float channels

Warning: MultiProc use should be avoided when reading several files in a batch, it is not thread safe. You should better multi process instances of mdf rather than using `multiproc` in mdf class (see implementation of `mdfconverter`)

resample (*sampling=None, channel=None, master_channel=None*)

Resamples as much as possible all data groups into one data group having defined sampling interval or sharing same defined master channel

Parameters

- **sampling** (*float, optional*) –
resampling interval, None by default. If None, will rely on `channel` or `master_channel` parameters to define reference data group. If both are undefined, picking the first master

- **or | and **** (****) –
- **channel** (*str*, *optional*) – channel name to be resampled
- **or | and **** –
- **master_channel** (*str*, *optional*) – master channel name to be used as reference

Notes

1. resampling will be applied only to master channels that have same type as the one given by channel or master_channel parameters (applicable only to mdf4)
2. resampling will convert all your channels so be careful for big files and memory consumption

resample_group (*sampling*, *channel*, *new_master_data=None*)

Resamples one channel along with its dataGroup

Parameters

- **sampling** (*float*) – resampling interval
- **channel** (*str*) – channel name to be resampled (could be the master channel)
- **new_master_data** (*array*, *optional*) – master channel data to be applied to the group identified by channel

Notes

Resampling will convert all channels so be careful for big files and memory consumption

return_pandas_dataframe (*master_channel_name*)

returns a dataframe of a raster described by its master channel name

Parameters **master_channel_name** (*str*) – master channel name, key to a raster to be returned as pandas dataframe

Returns

Return type pandas dataframe of raster or data group

write (*file_name=None*, *compression=False*, *column_oriented=False*)

Writes simple mdf file, same format as originally read, default is 4.x

Parameters

- **file_name** (*str*, *optional*) – Name of file If file name is not input, written file name will be the one read with appended ‘_new’ string before extension
- **compression** (*bool*) – Flag to store data compressed (from mdf version 4.1) If activated, will write in version 4.1 even if original file is in version 3.x
- **column_oriented** (*bool*) – Flag to store , column oriented channels

Notes

All channels will be converted, so size might be bigger than original file

class mdfreader.mdfreader.**MdfInfo**() -> new empty dictionary *dict(mapping)* -> new dictionary initialized from a mapping object's (key, value) pairs *dict(iterable)* -> new dictionary initialized as if via: *d = {}* for *k, v* in *iterable*: *d[k] = v* *dict(**kwargs)* -> new dictionary initialized with the name=value pairs in the keyword argument list. For example: *dict(one=1, two=2)*

Bases: dict

fid

fileName

filterChannelNames

list_channels (*file_name=None*)
Read MDF file blocks and returns a list of contained channels

Parameters **file_name** (*string*) – file name

Returns **nameList** – list of channel names

Return type list of string

mdfversion

read_info (*file_name=None, fid=None, minimal=0*)
Reads MDF file and extracts its complete structure

Parameters

- **file_name** (*str, optional*) – file name. If not input, uses fileName attribute
- **fid** (*file identifier, optional*) –
- **minimal** (*int*) – 0 will load every metadata 1 will load DG, CG, CN and CC 2 will load only DG

zipfile

MDF MODULE DOCUMENTATION

mdf_skeleton module describing basic mdf structure and methods

Created on Thu Sept 24 2015

Author Aymeric Rateau

2.1 Dependencies

- Python >3.4 <<http://www.python.org>>
- Numpy >1.6 <<http://numpy.scipy.org>>

2.2 mdf

class mdfreader.mdf.CompressedData

Bases: object

compression (*a*)

data compression method

Parameters *a* (*numpy array*) – data to be compresses

data

decompression ()

data decompression

Returns

Return type uncompressed numpy array

dtype

class mdfreader.mdf.MdfSkeleton () -> new empty dictionary dict(mapping) -> new dictionary initialized from a mapping object's (key, value) pairs dict(iterable) -> new dictionary initialized as if via: *d* = {} for *k*, *v* in iterable: *d*[*k*] = *v* dict(**kwargs) -> new dictionary initialized with the name=value pairs in the keyword argument list. For example: dict(one=1, two=2)

Bases: dict

MDFVersionNumber

add_channel (*channel_name*, *data*, *master_channel*, *master_type*=1, *unit*="", *description*="", *conversion*=None, *info*=None, *compression*=False, *identifier*=None)
adds channel to mdf dict.

Parameters

- **channel_name** (*str*) – channel name
- **data** (*numpy array*) – numpy array of channel's data
- **master_channel** (*str*) – master channel name
- **master_type** (*int*, *optional*) – master channel type : 0=None, 1=Time, 2=Angle, 3=Distance, 4=index
- **unit** (*str*, *optional*) – unit description
- **description** (*str*, *optional*) – channel description
- **conversion** (*info class*, *optional*) – conversion description from info class
- **info** (*info class for CNBlock*, *optional*) – used for CABlock axis creation and channel conversion
- **compression** (*bool*) – flag to ask for channel data compression
- **identifier** (*tuple*) – tuple of int and str following below structure: (data group number, channel group number, channel number), (channel name, channel source, channel path), (group name, group source, group path)

add_metadata (*author*="", *organisation*="", *project*="", *subject*="", *comment*="", *time*="")
adds basic metadata to mdf class

Parameters

- **author** (*str*) – author of file
- **organisation** (*str*) – organisation of author
- **project** (*str*) –
- **subject** (*str*) –
- **comment** (*str*) –
- **time** (*float (epoch)*) –

Notes

All fields are optional, default being empty string

convertAfterRead

convertTables

copy()

copy a mdf class

Returns **mdf_skeleton** – copy of a mdf_skeleton class

Return type class instance

fid

fileMetadata

fileName

filterChannelNames**get_channel** (*channel_name*)

Extract channel dict from mdf structure

Parameters **channel_name** (*str*) – channel name**Returns****Return type** channel dictionary containing data, description, unit, etc.**get_channel_conversion** (*channel_name*)

Extract channel conversion dict from mdf structure

Parameters **channel_name** (*str*) – channel name**Returns****Return type** channel conversion dict**get_channel_desc** (*channel_name*)

Extract channel description information from mdf structure

Parameters **channel_name** (*str*) – channel name**Returns****Return type** channel description string**get_channel_master** (*channel_name*)

Extract channel master name from mdf structure

Parameters **channel_name** (*str*) – channel name**Returns****Return type** channel master name string**get_channel_master_type** (*channel_name*)

Extract channel master type information from mdf structure

Parameters **channel_name** (*str*) – channel name**Returns** channel mater type integer**Return type** 0=None, 1=Time, 2=Angle, 3=Distance, 4=index**get_channel_unit** (*channel_name*)

Returns channel unit string Implemented for a future integration of pint

Parameters **channel_name** (*str*) – channel name**Returns** unit string description**Return type** str**get_invalid_bit** (*channel_name*)**get_invalid_channel** (*channel_name*)**info****masterChannelList****multiProc****remove_channel** (*channel_name*)

removes channel from mdf dict.

Parameters `channel_name` (*str*) – channel name

Returns

Return type value of mdf dict key=`channel_name`

remove_channel_conversion (*channel_name*)

removes conversion key from mdf channel dict.

Parameters `channel_name` (*str*) – channel name

Returns

Return type removed value from dict

rename_channel (*channel_name*, *new_name*)

Modifies name of channel

Parameters

- `channel_name` (*str*) – channel name
- `new_name` (*str*) – new channel name

set_channel_attachment (*channel_name*, *attachment*)

Modifies channel attachment

Parameters

- `channel_name` (*str*) – channel name
- `attachment` – channel attachment

set_channel_conversion (*channel_name*, *conversion*)

Modifies conversion dict of channel

Parameters

- `channel_name` (*str*) – channel name
- `conversion` (*dict*) – conversion dictionary

set_channel_data (*channel_name*, *data*, *compression=False*)

Modifies data of channel

Parameters

- `channel_name` (*str*) – channel name
- `data` (*numpy array*) – channel data
- `compression` (*bool or str*) – trigger for data compression

set_channel_desc (*channel_name*, *desc*)

Modifies description of channel

Parameters

- `channel_name` (*str*) – channel name
- `desc` (*str*) – channel description

set_channel_master (*channel_name*, *master*)

Modifies channel master name

Parameters

- `channel_name` (*str*) – channel name

- **master** (*str*) – master channel name

set_channel_master_type (*channel_name*, *master_type*)

Modifies master channel type

Parameters

- **channel_name** (*str*) – channel name
- **master_type** (*int*) – master channel type

set_channel_unit (*channel_name*, *unit*)

Modifies unit of channel

Parameters

- **channel_name** (*str*) – channel name
- **unit** (*str*) – channel unit

set_invalid_bit (*channel_name*, *bit_position*)

returns the invalid bit position of channel

Parameters

- **channel_name** (*str*) – channel name
- **bit_position** – invalid bit position of channel within invalid channel bytes

Returns

Return type bit position

set_invalid_channel (*channel_name*, *invalid_channel*)

zipfile

MDF3READER MODULE DOCUMENTATION

Measured Data Format file reader module for version 3.x

Author Aymeric Rateau

Created on Sun Oct 10 12:57:28 2010

3.1 mdf3reader

class mdfreader.mdf3reader.**DATA** (*fid, pointer*)

Bases: dict

DATA class is organizing record classes itself made of channel. This class inherits from dict. Keys are corresponding to channel group recordID. A DATA class corresponds to a data block, a dict of record classes (one per channel group). Each record class contains a list of channel class representing the structure of channel record.

fid

file identifier

Type io.open

pointerToData

position of Data block in mdf file

Type int

BlockLength

total size of data block

Type int

add_record (*record*)

Adds a new record in DATA class dict

read (*channelSet*)

Reads data block

load_sorted (*record, nameList=None*)

Reads sorted data block from record definition

load_unsorted (*nameList=None*)

Reads unsorted data block, not yet implemented

add_record (*record*)

Adds a new record in DATA class dict

Parameters **record** (*class*) – channel group definition listing record channel classes

load_sorted (*record*, *name_list=None*)

Reads sorted data block from record definition

Parameters

- **record** (*class*) – channel group definition listing record channel classes
- **name_list** (*set of str, optional*) – list of channel names

Returns

Return type numpy recarray of data

load_unsorted (*name_set=None*)

Reads unsorted data block from record definition

Parameters **name_set** (*set of str, optional*) – set of channel names

Returns

Return type numpy recarray of data

read (*channel_set*, *file_name*)

Reads data block

Parameters

- **channel_set** (*set of str, optional*) – list of channel names
- **file_name** (*str*) – name of file

```
class mdfreader.mdf3reader.Mdf3 (file_name=None,           channel_list=None,           con-  
                                vert_after_read=True,       filter_channel_names=False,  
                                no_data_loading=False,      compression=False,      con-  
                                vert_tables=False, metadata=2)
```

Bases: `mdfreader.mdf.MdfSkeleton`

mdf file version 3.0 to 3.3 class

fileName

file name

Type str

MDFVersionNumber

mdf file version number

Type int

masterChannelList

Represents data structure: a key per master channel with corresponding value containing a list of channels
One key or master channel represents then a data group having same sampling interval.

Type dict

multiProc

Flag to request channel conversion multi processed for performance improvement. One thread per data group.

Type bool

convertAfterRead

flag to convert raw data to physical just after read

Type bool

filterChannelNames

flag to filter long channel names from its module names separated by ‘.’

Type bool

fileMetadata

file metadata with minimum keys: author, organisation, project, subject, comment, time, date

Type dict

read3 (*fileName=None, info=None, multiProc=False, channelList=None, convertAfterRead=True*)

Reads mdf 3.x file data and stores it in dict

_get_channel_data3 (*channelName*)

Returns channel numpy array

_convert_channel13 (*channelName*)

converts specific channel from raw to physical data according to CCBlock information

_convert_all_channel13 ()

Converts all channels from raw data to converted data according to CCBlock information

write3 (*fileName=None*)

Writes simple mdf 3.3 file

read3 (*file_name=None, info=None, multi_processed=False, channel_list=None, convert_after_read=True, filter_channel_names=False, compression=False, metadata=2*)

Reads mdf 3.x file data and stores it in dict

Parameters

- **file_name** (*str, optional*) – file name
- **info** (*mdfinfo3.info3 class*) – info3 class containing all MDF Blocks
- **multi_processed** (*bool*) – flag to activate multiprocessing of channel data conversion
- **channel_list** (*list of str, optional*) – list of channel names to be read If you use channelList, reading might be much slower but it will save you memory. Can be used to read big files
- **convert_after_read** (*bool, optional*) – flag to convert channel after read, True by default If you use convertAfterRead by setting it to false, all data from channels will be kept raw, no conversion applied. If many float are stored in file, you can gain from 3 to 4 times memory footprint To calculate value from channel, you can then use method .get_channel_data()
- **filter_channel_names** (*bool, optional*) – flag to filter long channel names from its module names separated by ‘.’
- **compression** (*bool, optional*) – flag to activate data compression with blosc
- **metadata** (*int, optional, default = 2*) – Reading metadata has impact on performance, especially for mdf 4.x using xml. 2: minimal metadata reading (mostly channel blocks) 1: used for noDataLoading 0: all metadata reading

write3 (*file_name=None*)

Writes simple mdf 3.3 file

Parameters file_name (*str, optional*) – Name of file If file name is not input, written file name will be the one read with appended ‘_new’ string before extension

Notes

All channels will be converted to physical data, so size might be bigger than original file

class mdfreader.mdf3reader.**Record**(*data_group, channel_group*)

Bases: list

record class lists Channel classes, it is representing a channel group

CGrecordLength

length of record from channel group block information in Byte

Type int

recordLength

length of record from channels information in Byte

Type int

numberOfRecords

number of records in data block

Type int

recordID

recordID corresponding to channel group

Type int

recordIDnumber

size of recordID

Type int

dataGroup

data group number

Type int:

channelGroup

channel group number

Type int

numpyDataRecordFormat

list of numpy (dtype) for each channel

Type list

dataRecordName

list of channel names used for recarray attribute definition

Type list

master

define name and number of master channel

Type dict

recordToChannelMatching

helps to identify nested bits in byte

Type dict

channelNames

channel names to be stored, useful for low memory consumption but slow

Type set

hiddenBytes

flag in case of non declared channels in record

Type Bool, False by default

byte_aligned

flag for byte aligned record

Type Bool, True by default

addChannel (*info*, *channelNumber*)

loadInfo (*info*)

readSortedRecord (*fid*, *pointer*, *channelSet=None*)

readRecordBuf (*buf*, *channelSet=None*)

readRecordBits (*bita*, *channelSet=None*)

add_channel (*info*, *channel_number*)

add a channel in class

Parameters

- **info** (*mdfinfo3.info3 class*) –
- **channel_number** (*int*) – channel number in mdfinfo3.info3 class

load_info (*info*)

gathers records related from info class

Parameters **info** (*mdfinfo3.info3 class*) –

read_record_bits (*bit_stream*, *channel_set=None*)

read stream of record bits by bits in case of not aligned or hidden bytes

Parameters

- **bit_stream** (*stream*) – stream of bytes read in file
- **channel_set** (*Set of str, optional*) – list of channel to read

Returns **rec** – returns dictionary of channel with its corresponding values

Return type dict

read_record_buf (*buf*, *channel_set=None*)

read stream of record bytes

Parameters

- **buf** (*stream*) – stream of bytes read in file
- **channel_set** (*Set of str, optional*) – list of channel to read

Returns **rec** – returns dictionary of channel with its corresponding values

Return type dict

read_sorted_record (*fid*, *pointer*, *channel_set=None*)

reads record, only one channel group per data group

Parameters

- **fid** – file identifier

- **pointer** – position in file of data block beginning
- **channel_set** (*Set of str, optional*) – list of channel to read

Returns **rec** – contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Return type numpy recarray

Notes

If channelSet is None, read data using `numpy.core.records.fromfile` that is rather quick. However, in case of large file, you can use channelSet to load only interesting channels or only one channel on demand, but be aware it might be much slower.

MDFINFO3 MODULE DOCUMENTATION

Measured Data Format blocks parser for version 3.x

Created on Thu Dec 9 12:57:28 2014

Author Aymeric Rateau

4.1 Dependencies

- Python >3.4 <<http://www.python.org>>
- Numpy >1.14 <<http://numpy.scipy.org>>

4.2 mdinfo3

class `mdfreader.mdinfo3.Info3()` -> new empty dictionary *dict(mapping)* -> new dictionary initialized from a mapping object's (key, value) pairs *dict(iterable)* -> new dictionary initialized as if via: *d = {}* for *k, v* in *iterable*: *d[k] = v* *dict(**kwargs)* -> new dictionary initialized with the *name=value* pairs in the keyword argument list. For example: *dict(one=1, two=2)*

Bases: `dict`

clean_dg_info (*dg*)

delete CN,CC and CG blocks related to data group

Parameters *dg* (*int*) – data group number

fid

fileName

filterChannelNames

list_channels3 (*file_name=None, fid=None*)

reads data, channel group and channel blocks to list channel names

file_name

file name

Type `str`

Returns

Return type list of channel names

read_cg_block (*fid*, *dg*, *minimal=0*)
read all CG blocks and relying CN & CC

Parameters

- **fid** (*float*) – file identifier
- **dg** (*int*) – data group number
- **minimal** (*int*) – 0 will load every metadata 1 will load DG, CG, CN and CC 2 will load only DG

read_info3 (*fid*, *minimal=0*)
read all file blocks except data

Parameters

- **fid** (*float*) – file identifier
- **minimal** (*int*) – 0 will load every metadata 1 will load DG, CG, CN and CC 2 will load only DG

`mdfreader.mdinfo3.read_cc_block` (*fid*, *pointer*)
channel conversion block reading

`mdfreader.mdinfo3.read_ce_block` (*fid*, *pointer*)
reads source block

`mdfreader.mdinfo3.read_cg_block` (*fid*, *pointer*)
channel block reading

`mdfreader.mdinfo3.read_cn_block` (*fid*, *pointer*)
channel block reading

`mdfreader.mdinfo3.read_dg_block` (*fid*, *pointer*)
data group block reading

`mdfreader.mdinfo3.read_hd_block` (*fid*, *pointer*, *version=0*)
header block reading

`mdfreader.mdinfo3.read_tx_block` (*fid*, *pointer*)
reads text block

MDF4READER MODULE DOCUMENTATION

Measured Data Format file reader module for version 4.x.

Author Aymeric Rateau

Created on Thu Dec 10 12:57:28 2013

5.1 Dependencies

- Python >3.4 <<http://www.python.org>>
- Numpy >1.6 <<http://numpy.scipy.org>>
- bitarray to parse bits in not aligned bytes
- SymPy to convert channels with formula if needed
- zlib to uncompress data block if needed

5.2 mdf4reader

class mdfreader.mdf4reader.**Data**() -> new empty dictionary dict(mapping) -> new dictionary initialized from a mapping object's (key, value) pairs dict(iterable) -> new dictionary initialized as if via: `d = {}` for `k, v` in iterable: `d[k] = v` dict(**kwargs) -> new dictionary initialized with the `name=value` pairs in the keyword argument list. For example: `dict(one=1, two=2)`

Bases: dict

add_record(record)

Adds a new record in Data class dict.

Parameters **record** (class) – channel group definition listing record channel classes

fid

load(record, info, name_list=None, sorted_flag=True, vlsd=None)

Reads data block from record definition

Parameters

- **record** (class) – channel group definition listing record channel classes
- **info** (class) – contains blocks
- **name_list** (list of str, optional) – list of channel names

- **sorted_flag** (*bool, optional*) – flag to know if data block is sorted (only one Channel Group in block) or unsorted (several Channel Groups identified by a recordID). As unsorted block can contain CG records in random order, block is processed iteratively, not in raw like sorted -> much slower reading
- **vlsd** (*array or None*) – indicate a sd block, compressed (DZ) or not (SD)

Returns

Return type numpy recarray of data

pointer_to_data

read (*channel_set, info, filename*)

Reads data block

Parameters

- **channel_set** (*set of str*) – set of channel names
- **info** (*info object*) – contains blocks structures
- **filename** – name of file ot read

read_data_list (*field, nBytes, temps, record, info, name_list, sorted_flag, vlstd*)

read_record (*record_id, info, buf*)

read record from a buffer

Parameters

- **record_id** (*int*) – record identifier
- **info** (*class*) – contains blocks
- **buf** (*str*) – buffer of data from file to be converted to channel raw data

type

```
class mdfreader.mdf4reader.Mdf4 (file_name=None,          channel_list=None,          con-
                                vert_after_read=True,      filter_channel_names=False,
                                no_data_loading=False,      compression=False,      con-
                                vert_tables=False, metadata=2)
```

Bases: *mdfreader.mdf.MdfSkeleton*

mdf file reader class from version 4.0 to 4.1.1

fileName

file name

Type str

MDFVersionNumber

mdf file version number

Type int

masterChannelList

Represents data structure: a key per master channel with corresponding value containing a list of channels
One key or master channel represents then a data group having same sampling interval.

Type dict

multiProc

Flag to request channel conversion multi processed for performance improvement. One thread per data group.

Type bool

convertAfterRead

flag to convert raw data to physical just after read

Type bool

filterChannelNames

flag to filter long channel names from its module names separated by ‘.’

Type bool

fileMetadata

file metadata with minimum keys : author, organisation, project, subject, comment, time, date

Type dict

read4 (*fileName=None, info=None, multiProc=False, channelList=None, convertAfterRead=True*)

Reads mdf 4.x file data and stores it in dict

_get_channel_data_4 (*channelName*)

Returns channel numpy array

_convert_channel_data_4 (*channel, channel_name, convert_tables, multiProc=False, Q=None*)

select right conversion and calculates it

_convert_channel_4 (*channelName*)

converts specific channel from raw to physical data according to CCBlock information

_convert_all_channel_4 ()

Converts all channels from raw data to converted data according to CCBlock information

write4 (*file_name=None, compression=False*)

writes mdf 4.1 file

apply_invalid_bit (*channel_name*)

mask data from invalid bit channel if existing

get_channel_name_4 (*name, path*)

returns a list of tuples

apply_all_invalid_bit ()

Mask data of all channels based on its invalid bit definition if there is

apply_invalid_bit (*channel_name*)

Mask data of channel based on its invalid bit definition if there is

Parameters **channel_name** (*str*) – Name of channel

get_channel_name4 (*name, path*)

finds mdf channel name from name and path

Parameters

- **name** (*str*) – channel name
- **path** (*str*) – source path or name, or channel group name, source name or path

Returns

Return type list of tuples (channel_name, (ndg, ncg, ncn))

get_invalid_mask (*channel_name*)

read4 (*file_name=None, info=None, multi_processed=False, channel_list=None, convert_after_read=True, filter_channel_names=False, compression=False, metadata=2*)

Reads mdf 4.x file data and stores it in dict

Parameters

- **file_name** (*str, optional*) – file name
- **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks
- **multi_processed** (*bool*) – flag to activate multiprocessing of channel data conversion
- **channel_list** (*list of str, optional*) – list of channel names to be read If you use channelList, reading might be much slower but it will save you memory. Can be used to read big files
- **convert_after_read** (*bool, optional*) – flag to convert channel after read, True by default If you use convertAfterRead by setting it to false, all data from channels will be kept raw, no conversion applied. If many float are stored in file, you can gain from 3 to 4 times memory footprint To calculate value from channel, you can then use method `.get_channel_data()`
- **filter_channel_names** (*bool, optional*) – flag to filter long channel names from its module names separated by ‘.’
- **compression** (*bool, optional*) – flag to activate data compression with blosc
- **metadata** (*int, optional, default = 2*) – Reading metadata has impact on performance, especially for mdf 4.x using xml. 2: minimal metadata reading (mostly channel blocks) 1: used for noDataLoading 0: all metadata reading, including Source Information, Attachment, etc..

write4 (*file_name=None, compression=False, column_oriented=False*)

Writes simple mdf file

Parameters

- **file_name** (*str, optional*) – Name of file If file name is not input, written file name will be the one read with appended ‘_new’ string before extension
- **compression** (*bool*) – flag to store data compressed
- **column_oriented** (*bool*) – flag to store data in columns, faster reading channel by channel and not jumping in records

Notes

All channels will be converted to physical data, so size might be bigger than original file

class mdfreader.mdf4reader.**Record**() -> new empty dictionary dict(mapping) -> new dictionary initialized from a mapping object's (key, value) pairs dict(iterable) -> new dictionary initialized as if via: `d = {}` for `k, v` in iterable: `d[k] = v` dict(**kwargs) -> new dictionary initialized with the name=value pairs in the keyword argument list. For example: `dict(one=1, two=2)`

Bases: dict

CANOpen

CGrecordLength

Flags

MLSD

VLSD

VLSD_CG

add_channel (*info*, *channel_number*)
add a channel in class

Parameters

- **info** (*mdfinfo4.info4 class*) –
- **channel_number** (*int*) – channel number in mdfinfo4.info4 class

byte_aligned

channelGroup

channelNames

dataGroup

dataRecordName

generate_chunks ()
calculate data split

Returns

Return type (*n_record_chunk*, *chunk_size*)

hiddenBytes

initialise_reccarray (*info*, *channel_set*, *n_records*, *dtype=None*, *channels_indexes=None*)
Initialise reccarray

Parameters

- **info** (*info class*) –
- **channel_set** (*set of str, optional*) – set of channel to read
- **n_records** (*int*) – number of records
- **dtype** (*numpy dtype, optional*) –
- **channels_indexes** (*list of int, optional*) –

Returns **rec** – contains a matrix of raw data in a reccarray (attributes corresponding to channel name)

Return type numpy reccarray

invalid_channel

load_info (*info*)
gathers records related from info class

Parameters **info** (*mdfinfo4.info4 class*) –

master

numberOfRecords

numpyDataRecordFormat

read_all_channels_sorted_record (*fid*)
reads all channels from file using numpy fromstring, chunk by chunk

Parameters **fid** – file identifier

Returns `rec` – contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Return type numpy recarray

read_channels_from_bytes (*bit_stream*, *info*, *channel_set=None*, *n_records=None*, *dtype=None*, *channels_indexes=None*)

reads stream of record bytes using dataRead module if available otherwise bitarray

Parameters

- **bit_stream** (*stream*) – stream of bytes
- **info** (*info class*) –
- **channel_set** (*set of str, optional*) – set of channel to read
- **n_records** (*int*) – number of records
- **dtype** (*numpy dtype*) –
- **channels_indexes** (*list of int*) –

Returns `rec` – contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Return type numpy recarray

read_channels_from_bytes_fallback (*bit_stream*, *info*, *channel_set=None*, *n_records=None*, *dtype=None*, *channels_indexes=None*)

reads stream of record bytes using bitarray in case no dataRead available

Parameters

- **bit_stream** (*stream*) – stream of bytes
- **info** (*info class*) –
- **channel_set** (*set of str, optional*) – set of channel to read
- **n_records** (*int*) – number of records
- **dtype** (*numpy dtype*) –
- **channels_indexes** (*list of int*) –

Returns `rec` – contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Return type numpy recarray

read_not_all_channels_sorted_record (*fid*, *info*, *channel_set*)

reads channels from file listed in channelSet

Parameters

- **fid** – file identifier
- **info** (*info class*) –
- **channel_set** (*set of str, optional*) – set of channel to read

Returns `rec` – contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Return type numpy recarray

read_record_buf (*buf*, *info*, *channel_set=None*)

read stream of record bytes

Parameters

- **buf** (*stream*) – stream of bytes read in file
- **info** (*class*) – contains blocks structure
- **channel_set** (*set of str, optional*) – set of channel to read

Returns **rec** – returns dictionary of channel with its corresponding values

Return type dict

read_sorted_record (*fid, info, channel_set=None*)

reads record, only one channel group per datagroup

Parameters

- **fid** – file identifier
- **info** – info class
- **channel_set** (*set of str, optional*) – set of channel to read

Returns **rec** – contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Return type numpy recarray

Notes

If channelSet is None, read data using `numpy.core.records.fromfile` that is rather quick. However, in case of large file, you can use channelSet to load only interesting channels or only one channel on demand, but be aware it might be much slower.

read_unique_channel (*fid, info*)

reads all channels from file using numpy fromstring, chunk by chunk

Parameters

- **fid** – file identifier
- **info** – info class

Returns **rec** – contains a matrix of raw data in a recarray (attributes corresponding to channel name)

Return type numpy recarray

recordID

recordIDCFormat

recordIDsize

recordLength

recordToChannelMatching

unique_channel_in_DG

MDFINFO4 MODULE DOCUMENTATION

Measured Data Format blocks parser for version 4.x

Created on Sun Dec 15 12:57:28 2013

Author Aymeric Rateau

6.1 mdinfo4

```
class mdfreader.mdinfo4.ATBlock (fid, pointer)
    Bases: dict
    reads Attachment block and saves in class dict

class mdfreader.mdinfo4.CABlock
    Bases: dict
    reads Channel Array block and saves in class dict
    load (byte_offset_base)
    read (fid, pointer)
    write (fid)

class mdfreader.mdinfo4.CCBlock
    Bases: dict
    reads Channel Conversion block and saves in class dict
    read_cc (fid, pointer)

class mdfreader.mdinfo4.CGBlock (fid=None, pointer=None)
    Bases: dict
    reads Channel Group block and saves in class dict
    read_cg (fid, pointer)
    write (fid)

class mdfreader.mdinfo4.CHBlock (fid, pointer)
    Bases: dict
    reads Channel Hierarchy block and saves in class dict

class mdfreader.mdinfo4.CNBlock
    Bases: dict
    reads Channel block and saves in class dict
```

read_cn (**kargs)

write (fid)

class mdfreader.mdinfo4.**CommentBlock**

Bases: dict

reads or writes Comment block and saves in class dict

load (data, md_type)

read_cm_at (fid, pointer)

reads Comment block from attachment block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_cc (fid, pointer)

reads Comment block from channel conversion block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_cc_unit (fid, pointer)

reads Comment block for channel conversion unit

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_cg (fid, pointer)

reads Comment block from channel group block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_ch (fid, pointer)

reads Comment block from file channel hierarchy block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_cn (fid, pointer, minimal=True)

reads Comment block from channel block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file
- **minimal** (*boolean*) – flag to reduce metadata parsing

read_cm_cn_unit (fid, pointer)

reads Comment block for channel unit

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_dg (*fid, pointer*)

reads Comment block from data group block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_ev (*fid, pointer*)

reads Comment block from event block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_fh (*fid, pointer*)

reads Comment block from file history block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_hd (*fid, pointer*)

reads Comment block from header block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_header (*fid, pointer*)

reads Comment block header

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_cm_si (*fid, pointer*)

reads Comment block from source information block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_tx (*fid, pointer*)

reads TX block

Parameters

- **fid** – file identifier
- **pointer** (*int*) – position in file

read_xml (*fid*)
reads Comment block xml and objectifies it

Parameters

- **fid** – file identifier
- **block** (*Metadata*) –
- **normal 0 at end** (*removes*) –

write (*fid*)

class mdfreader.mdinfo4.DGBlock (*fid=None, pointer=None*)

Bases: dict

reads Data Group block and saves in class dict

read_dg (*fid, pointer*)

write (*fid*)

class mdfreader.mdinfo4.DIBlock () -> new empty dictionary dict(mapping) -> new dictionary initialized from a mapping object's (key, value) pairs
dict(iterable) -> new dictionary initialized as if via: d = {}
for k, v in iterable: d[k] = v dict(**kwargs) -> new dictionary
initialized with the name=value pairs in the keyword argument
list. For example: dict(one=1, two=2)

Bases: dict

load (*invalid_bytes, nRecords, pointer*)

write (*fid, data*)

class mdfreader.mdinfo4.DLBlock

Bases: dict

reads List Data block

read_dl (*fid, link_count*)

write (*fid, chunks*)

class mdfreader.mdinfo4.DTBlock () -> new empty dictionary dict(mapping) -> new dictionary initialized from a mapping object's (key, value) pairs
dict(iterable) -> new dictionary initialized as if via: d = {}
for k, v in iterable: d[k] = v dict(**kwargs) -> new dictionary
initialized with the name=value pairs in the keyword argument
list. For example: dict(one=1, two=2)

Bases: dict

load (*record_byte_offset, nRecords, pointer*)

write (*fid, data*)

class mdfreader.mdinfo4.DVBlock () -> new empty dictionary dict(mapping) -> new dictionary initialized from a mapping object's (key, value) pairs
dict(iterable) -> new dictionary initialized as if via: d = {}
for k, v in iterable: d[k] = v dict(**kwargs) -> new dictionary
initialized with the name=value pairs in the keyword argument
list. For example: dict(one=1, two=2)

Bases: dict

load (*record_byte_offset, nRecords, pointer*)

```

    write (fid, data)

```

class mdfreader.mdinfo4.**DZBlock**

Bases: dict

reads Data List block

static decompress_data_block (*block*, *zip_type*, *zip_parameter*, *org_data_length*)
decompress datablock.

Parameters

- **block** (*bytes*) – raw data compressed
- **zip_type** (*int*) – 0 for non transposed, 1 for transposed data
- **zip_parameter** (*int*) – first dimension of matrix to be transposed
- **org_data_length** (*int*) – uncompressed data length

Returns

Return type uncompressed raw data

```

    read_dz (fid)
    write (fid, data, record_length)

```

class mdfreader.mdinfo4.**EVBlock** (*fid*, *pointer*)

Bases: dict

reads Event block and saves in class dict

class mdfreader.mdinfo4.**FHBlock** (*fid=None*, *pointer=None*)

Bases: dict

reads File History block and save in class dict

```

    read (fid, pointer)
    write (fid)

```

class mdfreader.mdinfo4.**HDBlock** (*fid=None*)

Bases: dict

reads Header block and save in class dict

```

    read (fid=None)
    write (fid)

```

class mdfreader.mdinfo4.**HLBlock**

Bases: dict

reads Header List block

```

    load (record_byte_offset, n_records, position)
    read_hl (fid)
    write (fid, data)

```

class mdfreader.mdinfo4.**IDBlock** (*fid=None*)

Bases: dict

reads or writes ID Block

```

    read (fid)
        reads IDBlock

```

write (*fid*)
Writes IDBlock

class mdfreader.mdinfo4.**Info4** () -> new empty dictionary dict(mapping) -> new dictionary initialized from a mapping object's (key, value) pairs dict(iterable) -> new dictionary initialized as if via: *d* = {} for *k*, *v* in iterable: *d*[*k*] = *v* dict(**kwargs) -> new dictionary initialized with the name=value pairs in the keyword argument list. For example: dict(one=1, two=2)

Bases: dict

clean_dg_info (*dg*)
delete CN,CC and CG blocks related to data group

Parameters *dg* (*int*) – data group number

fid

fileName

filterChannelNames

list_channels4 (*file_name=None*, *fid=None*)
Read MDF file and extract its complete structure

Parameters

- **file_name** (*str*) – file name
- **fid** –

Returns

Return type list of channel names contained in file

read_cg_block (*fid*, *dg*, *cg*, *pointer*, *vlsd_cg_block*, *channel_name_list=False*, *minimal=0*)
reads one Channel Group block

Parameters

- **fid** (*float*) – file identifier
- **dg** (*int*) – data group number
- **cg** (*int*) – channel group number
- **channel_name_list** (*bool*) – Flag to reads only channel blocks for listChannels4 method
- **minimal** (*flag*) – to activate minimum content reading for raw data fetching

Returns *vlsd_cg_block*

Return type boolean

read_cg_blocks (*fid*, *dg*, *channel_name_list=False*, *minimal=0*)
reads Channel Group blocks linked to same Data Block dg

Parameters

- **fid** (*float*) – file identifier
- **dg** (*int*) – data group number
- **channel_name_list** (*bool*) – Flag to reads only channel blocks for listChannels4 method
- **minimal** (*flag*) – to activate minimum content reading for raw data fetching

read_ch_block (*fid, pointer*)
reads channel hierarchy Blocks

Parameters

- **fid** (*identifier*) – file identifier
- **pointer** (*int*) – position of EVBlock in file

Returns

Return type channel hierarchy Blocks in a dict

read_cn_block (*fid, pointer, dg, cg, mlsd_channels, vlsd, minimal, channel_name_list*)
reads single Channel block

Parameters

- **fid** (*float*) – file identifier
- **pointer** (*int*) – position in file
- **dg** (*int*) – data group number
- **cg** (*int*) – channel group number in data group
- **mlsd_channels** (*list of int*) – list of maximum length data channel numbers
- **minimal** (*flag*) – to activate minimum content reading for raw data fetching
- **channel_name_list** (*bool*) – Flag to reads only channel blocks for listChannels4 method

Returns

- **cn** (*integer*) – channel number
- *MLSDChannels* list of appended Maximum Length Sampling Data channels
- **vlsd** (*boolean*)

read_cn_blocks (*fid, dg, cg, channel_name_list=False, minimal=0*)
reads Channel blocks link to CG Block

Parameters

- **fid** (*float*) – file identifier
- **dg** (*int*) – data group number
- **cg** (*int*) – channel group number in data group
- **channel_name_list** (*bool*) – Flag to reads only channel blocks for listChannels4 method
- **minimal** (*flag*) – to activate minimum content reading for raw data fetching

Returns vlsd

Return type boolean

read_dg_block (*fid, channel_name_list=False, minimal=0*)
reads Data Group Blocks

Parameters

- **fid** (*float*) – file identifier

- **channel_name_list** (*bool*) – Flag to reads only channel blocks for listChannels4 method
- **minimal** (*flag*) – to activate minimum content reading for raw data fetching

static read_ev_block (*fid, pointer*)
reads Events Blocks

Parameters

- **fid** (*identifier*) – file identifier
- **pointer** (*int*) – position of EVBlock in file

Returns

Return type Event Blocks in a dict

read_info (*fid, minimal*)
read all file blocks except data

Parameters

- **fid** (*identifier*) – file identifier
- **minimal** (*flag*) – to activate minimum content reading for raw data fetching

static read_sr_block (*fid, pointer*)
reads Sample Reduction Blocks

Parameters

- **fid** (*float*) – file identifier
- **pointer** (*int*) – position of SRBlock in file

Returns

Return type Sample Reduction Blocks in a dict

unique_id (*ndg, ncg, ncn*)
generate unique id tuples

Parameters

- **ndg** (*int*) – data group number
- **ncg** (*int*) – channel group number
- **ncn** (*int*) – channel number

Returns tuples – (channel name, channel source, channel path), (group name, group source, group path)

Return type (data group number, channel group number, channel number),

zipfile

class mdfreader.mdinfo4.LDBlock

Bases: dict

reads List Data block

load (*record_byte_offset, n_records, position, invalid_bytes=0, column_oriented_flag=False*)

read_ld (*fid, link_count*)

write (*fid, data, invalid_data=None, compression_flag=False*)

write_DIV (*fid, pointer, block, data, dl_data, counter, data_pointer, record_length, chunk_size, n_records*)

write_DZ (*fid, pointer, data, dl_data, counter, data_pointer, record_length, chunk_size, dz_zip_type, dz_org_block_type*)

class mdfreader.mdinfo4.**SIBlock**

Bases: dict

reads Source Information block and saves in class dict

read_si (*fid, pointer*)

class mdfreader.mdinfo4.**SRBlock** (*fid, pointer*)

Bases: dict

reads Sample Reduction block and saves in class dict

CHANNEL MODULE DOCUMENTATION

Measured Data Format file reader module.

Author Aymeric Rateau

Created on Wed Oct 04 21:13:28 2017

`mdfreader.channel.PythonVersion`

Python version currently running, needed for compatibility of both python 3.4+

Type float

`mdfreader.channel.channel`

class `mdfreader.channel.Channel13` (*info*, *data_group*, *channel_group*, *channel_number*,
record_id_number)

Bases: object

Channel class gathers all about channel structure in a record

name

Name of channel

Type str

unit

channel unit

Type str, default empty string

desc

channel description

Type str

conversion

conversion dictionary

Type info class

channelNumber

channel number corresponding to `mdfinfo3.info3` class

Type int

signalDataType

signal type according to specification

Type int

bitCount
number of bits used to store channel record
Type int

nBytes_aligned
number of bytes (1 byte = 8 bits) taken by channel record
Type int

dataFormat
numpy dtype as string
Type str

CFormat
struct instance to convert from C Format
Type struct class instance

byteOffset
position of channel record in complete record in bytes
Type int

bitOffset
bit position of channel value inside byte in case of channel having bit count below 8
Type int

recAttributeName
channel name compliant to a valid python identifier (recarray attribute)
Type str

RecordFormat
dtype format used for numpy.core.records functions ((name_title,name),str_type)
Type list of str

channelType
channel type
Type int

posByteBeg
start position in number of bit of channel record in complete record
Type int

posByteEnd
end position in number of bit of channel record in complete record
Type int

bit_masking_needed
True if bit masking needed after data read
Type bool, default false

__init__ (*info, dataGroup, channelGroup, channelNumber, recordIDnumber*)
constructor

__str__ ()
to print class attributes

change_channel_name (*channel_group*)

rename duplicated channel name within unsorted channel groups

change_channel_name (*channel_group*)

In case of duplicate channel names within several channel groups for unsorted data, rename channel name

Parameters **channel_group** (*int*) – channelGroup number

class mdfreader.channel.**Channel4** (*data_group, channel_group, channel_number*)

Bases: object

CANOpen_offset ()

CANopen channel bytes offset

Returns

Return type integer, channel bytes offset

VLSD_CG_Flag

attachment (*fid, info*)

In case of sync channel attached to channel

Parameters

- **fid** (*class*) – file identifier
- **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type ATBlock class from mdfinfo4 module

bit_count (*info*)

calculates channel number of bits

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type integer corresponding to channel number of bits

bit_masking_need (*info*)

Valid if bit masking need

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type boolean True if channel needs bit masking, otherwise False

bit_offset (*info*)

channel data bit offset in record

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type integer, channel bit offset

byteOffset

c_format (*info*)

channel data C format

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type string data C format

c_format_structure (*info*)

channel data C format struct object

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type string data C format struct object

ca_block (*info*)

Extracts channel CA Block from info4

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type CABlock object from mdfinfo4 module

calc_byte_offset (*info*)

channel data bytes offset in record (without record id)

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type integer, channel bytes offset

calc_bytes (*info, aligned=True*)

calculates channel aligned bytes number

Parameters

- **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks
- **aligned** (*boolean*) – with or without aligned bytes

Returns

Return type number of bytes integer

change_channel_name (*channel_group*)

In case of duplicate channel names within several channel groups for unsorted data, rename channel name

Parameters **channel_group** (*int*) – channelGroup number

channelGroup

channelNumber

channel_sync_type (*info*)

Extracts channel sync type from info4

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

- *integer corresponding to channel sync type*
- *0 no sync, normal data*
- *1 time*
- *2 angle*
- *3 distance*
- *4 index*

channel_type (*info*)

Extracts channel type from info4

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

- *integer describing channel type*
- *0 normal channel*
- *1 variable length*
- *2 master channel*
- *3 virtual master channel*
- *4 sync channel*
- *5 max length data*
- *6 virtual data channel*

cn_block (*info*)

channel block

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type CNBlock class from mdfinfo4 module

conversion (*info*)

channel conversion CCBBlock

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type *CCBlock*

data (*info*)

returns data block pointer for VLSD, MLD or sync channels

dataGroup**data_format** (*info*)

channel numpy.core.records data format

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type string data format

desc (*info*)

channel description

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type channel description string

has_invalid_bit (*info*)**invalid_bit** (*info*)

extracts from info4 the channels valid bits positions

Parameters `info` (`mdfinfo4.info4 class`) – info4 class containing all MDF Blocks

Returns

Return type channel valid bit position

`is_ca_block` (`info`)

`isnumeric` (`info`)

check this is numeric channel from data type

Parameters `info` (`mdfinfo4.info4 class`) – info4 class containing all MDF Blocks

Returns

Return type boolean, true if numeric channel, otherwise false

`little_endian` (`info`)

check if channel is little endian

Parameters `info` (`mdfinfo4.info4 class`) – info4 class containing all MDF Blocks

Returns

Return type boolean

`nBytes_aligned`

`name`

`native_data_format` (`info`)

`numpy_format` (`info`)

channel numpy.core.records data format

Parameters `info` (`mdfinfo4.info4 class`) – info4 class containing all MDF Blocks

Returns endian, dataType

Return type string data format

`pos_bit_beg`

`pos_bit_begin` (`info`)

channel data bit starting position in record

Parameters `info` (`mdfinfo4.info4 class`) – info4 class containing all MDF Blocks

Returns

Return type integer, channel bit starting position

`pos_bit_end` (`info`)

channel data bit ending position in record

Parameters `info` (`mdfinfo4.info4 class`) – info4 class containing all MDF Blocks

Returns

Return type integer, channel bit ending position

`pos_byte_beg` (`info`)

channel data bytes starting position in record

Parameters `info` (`mdfinfo4.info4 class`) – info4 class containing all MDF Blocks

Returns

Return type integer, channel bytes starting position

pos_byte_end (*info*)

channel data bytes ending position in record

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type integer, channel bytes ending position

record_attribute_name ()

clean up channel name from unauthorised characters

Returns

Return type channel name compliant to python attributes names (for recarray)

record_id_size (*info*)

Extracts record id size from info4

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

- *integer describing record id size*
- *0 no record id used*
- *1 uint8*
- *2 uint16*
- *4 uint32*
- *8 uint64*

set (*info*)

channel initialisation

Parameters **info** (*mdfinfo4.info4 class*) –

set_CANOpen (*info, name*)

CANOpen channel intialisation

Parameters

- **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks
- **name** (*str*) – name of channel. Should be in ('ms', 'day', 'days', 'hour', 'month', 'minute', 'year')

set_invalid_bytes (*info*)

invalid_bytes channel initialisation

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

signal_data_type (*info, byte_aligned=True*)

extract signal data type from info4 class

Parameters

- **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks
- **byte_aligned** (*bool*) – flag activated if channel is part of a record byte aligned

Returns

- *integer corresponding to channel data type*
- *0 unsigned integer little endian*

- 1 unsigned integer big endian
- 2 signed integer little endian
- 3 signed integer big endian
- 4 float little endian
- 5 float big endian
- 6 string latin
- 7 string utf-8
- 9 string utf-16
- 10 byte array
- 11 mime sample
- 12 mime stream
- 13 CANopen date
- 14 CANopen time
- 15 LE Complex
- 16 BE Complex

type

unit (*info*)

channel unit

Parameters **info** (*mdfinfo4.info4 class*) – info4 class containing all MDF Blocks

Returns

Return type channel unit string

`mdfreader.channel.array_format4` (*signal_data_type, number_of_bytes*)

function returning numpy style string from channel data type and number of bits

Parameters

- **signal_data_type** (*int*) – channel data type according to specification
- **number_of_bytes** (*int*) – number of bytes taken by channel data in a record

Returns **endian, data_type** – numpy dtype format used by `numpy.core.records` to read channel raw data

Return type str

`mdfreader.channel.data_type_format4` (*signal_data_type, number_of_bytes*)

function returning C format string from channel data type and number of bits

Parameters

- **signal_data_type** (*int*) – channel data type according to specification
- **number_of_bytes** (*int*) – number of bytes taken by channel data in a record

Returns **data_type** – C format used by `fread` to read channel raw data

Return type str

INDICES AND TABLES

- `genindex`
- `modindex`
- `search`

PYTHON MODULE INDEX

m

- `mdfreader.channel`, [45](#)
- `mdfreader.mdf`, [13](#)
- `mdfreader.mdf3reader`, [19](#)
- `mdfreader.mdf4reader`, [27](#)
- `mdfreader.mdffinfo3`, [25](#)
- `mdfreader.mdffinfo4`, [35](#)
- `mdfreader.mdfreader`, [3](#)

Symbols

`__init__()` (*mdfreader.channel.Channel3* method), 46

`__str__()` (*mdfreader.channel.Channel3* method), 46

`_convert_all_channel3()` (*mdfreader.mdf3reader.Mdf3* method), 21

`_convert_all_channel4()` (*mdfreader.mdf4reader.Mdf4* method), 29

`_convert_channel3()` (*mdfreader.mdf3reader.Mdf3* method), 21

`_convert_channel4()` (*mdfreader.mdf4reader.Mdf4* method), 29

`_convert_channel_data4()` (*mdfreader.mdf4reader.Mdf4* method), 29

`_get_channel_data3()` (*mdfreader.mdf3reader.Mdf3* method), 21

`_get_channel_data4()` (*mdfreader.mdf4reader.Mdf4* method), 29

A

`add_channel()` (*mdfreader.mdf.MdfSkeleton* method), 13

`add_channel()` (*mdfreader.mdf3reader.Record* method), 23

`add_channel()` (*mdfreader.mdf4reader.Record* method), 31

`add_metadata()` (*mdfreader.mdf.MdfSkeleton* method), 14

`add_record()` (*mdfreader.mdf3reader.DATA* method), 19

`add_record()` (*mdfreader.mdf4reader.Data* method), 27

`addChannel()` (*mdfreader.mdf3reader.Record* method), 23

`apply_all_invalid_bit()` (*mdfreader.mdf4reader.Mdf4* method), 29

`apply_invalid_bit()` (*mdfreader.mdf4reader.Mdf4* method), 29

`array_format4()` (in module *mdfreader.channel*), 52

`ATBlock` (class in *mdfreader.mdfinfo4*), 35

`attachment()` (*mdfreader.channel.Channel4* method), 47

B

`bit_count()` (*mdfreader.channel.Channel4* method), 47

`bit_masking_need()` (*mdfreader.channel.Channel4* method), 47

`bit_masking_needed` (*mdfreader.channel.Channel3* attribute), 46

`bit_offset()` (*mdfreader.channel.Channel4* method), 47

`bitCount` (*mdfreader.channel.Channel3* attribute), 45

`bitOffset` (*mdfreader.channel.Channel3* attribute), 46

`BlockLength` (*mdfreader.mdf3reader.DATA* attribute), 19

`byte_aligned` (*mdfreader.mdf3reader.Record* attribute), 23

`byte_aligned` (*mdfreader.mdf4reader.Record* attribute), 31

`byteOffset` (*mdfreader.channel.Channel3* attribute), 46

`byteOffset` (*mdfreader.channel.Channel4* attribute), 47

C

`c_format()` (*mdfreader.channel.Channel4* method), 47

`c_format_structure()` (*mdfreader.channel.Channel4* method), 48

`ca_block()` (*mdfreader.channel.Channel4* method), 48

`CABlock` (class in *mdfreader.mdfinfo4*), 35

`calc_byte_offset()` (*mdfreader.channel.Channel4* method), 48

`calc_bytes()` (*mdfreader.channel.Channel4* method), 48

`CANOpen` (*mdfreader.mdf4reader.Record* attribute), 30

`CANOpen_offset()` (*mdfreader.channel.Channel4* method), 47

`CCBlock` (class in *mdfreader.mdfinfo4*), 35

`CFormat` (*mdfreader.channel.Channel3* attribute), 46

`CGBlock` (class in *mdfreader.mdfinfo4*), 35

`CGrecordLength` (*mdfreader.mdf3reader.Record* attribute), 22

- CGrecordLength (*mdfreader.mdf4reader.Record* attribute), 30
- change_channel_name() (*mdfreader.channel.Channel3* method), 46, 47
- change_channel_name() (*mdfreader.channel.Channel4* method), 48
- channel (in module *mdfreader.channel*), 45
- Channel3 (class in *mdfreader.channel*), 45
- Channel4 (class in *mdfreader.channel*), 47
- channel_sync_type() (*mdfreader.channel.Channel4* method), 48
- channel_type() (*mdfreader.channel.Channel4* method), 48
- channelGroup (*mdfreader.channel.Channel4* attribute), 48
- channelGroup (*mdfreader.mdf3reader.Record* attribute), 22
- channelGroup (*mdfreader.mdf4reader.Record* attribute), 31
- channelNames (*mdfreader.mdf3reader.Record* attribute), 22
- channelNames (*mdfreader.mdf4reader.Record* attribute), 31
- channelNumber (*mdfreader.channel.Channel3* attribute), 45
- channelNumber (*mdfreader.channel.Channel4* attribute), 48
- channelType (*mdfreader.channel.Channel3* attribute), 46
- CHBlock (class in *mdfreader.mdfinfo4*), 35
- clean_dg_info() (*mdfreader.mdfinfo3.Info3* method), 25
- clean_dg_info() (*mdfreader.mdfinfo4.Info4* method), 40
- cn_block() (*mdfreader.channel.Channel4* method), 49
- CNBlock (class in *mdfreader.mdfinfo4*), 35
- CommentBlock (class in *mdfreader.mdfinfo4*), 36
- CompressedData (class in *mdfreader.mdf*), 13
- compression() (*mdfreader.mdf.CompressedData* method), 13
- concat_mdf() (*mdfreader.mdfreader.Mdf* method), 5
- conversion (*mdfreader.channel.Channel3* attribute), 45
- conversion() (*mdfreader.channel.Channel4* method), 49
- convert_all_channel() (*mdfreader.mdfreader.Mdf* method), 4
- convert_all_channels() (*mdfreader.mdfreader.Mdf* method), 6
- convert_to_pandas() (*mdfreader.mdfreader.Mdf* method), 5, 6
- convertAfterRead (*mdfreader.mdf.MdfSkeleton* attribute), 14
- convertAfterRead (*mdfreader.mdf3reader.Mdf3* attribute), 20
- convertAfterRead (*mdfreader.mdf4reader.Mdf4* attribute), 29
- convertTables (*mdfreader.mdf.MdfSkeleton* attribute), 14
- copy() (*mdfreader.mdf.MdfSkeleton* method), 14
- cut() (*mdfreader.mdfreader.Mdf* method), 6
- ## D
- DATA (class in *mdfreader.mdf3reader*), 19
- Data (class in *mdfreader.mdf4reader*), 27
- data (*mdfreader.mdf.CompressedData* attribute), 13
- data() (*mdfreader.channel.Channel4* method), 49
- data_format() (*mdfreader.channel.Channel4* method), 49
- data_type_format4() (in module *mdfreader.channel*), 52
- dataFormat (*mdfreader.channel.Channel3* attribute), 46
- dataGroup (*mdfreader.channel.Channel4* attribute), 49
- dataGroup (*mdfreader.mdf3reader.Record* attribute), 22
- dataGroup (*mdfreader.mdf4reader.Record* attribute), 31
- dataRecordName (*mdfreader.mdf3reader.Record* attribute), 22
- dataRecordName (*mdfreader.mdf4reader.Record* attribute), 31
- decompress_data_block() (*mdfreader.mdfinfo4.DZBlock* static method), 39
- decompression() (*mdfreader.mdf.CompressedData* method), 13
- desc (*mdfreader.channel.Channel3* attribute), 45
- desc() (*mdfreader.channel.Channel4* method), 49
- DGBlock (class in *mdfreader.mdfinfo4*), 38
- DIBlock (class in *mdfreader.mdfinfo4*), 38
- DLBlock (class in *mdfreader.mdfinfo4*), 38
- DTBlock (class in *mdfreader.mdfinfo4*), 38
- dtype (*mdfreader.mdf.CompressedData* attribute), 13
- DVBlock (class in *mdfreader.mdfinfo4*), 38
- DZBlock (class in *mdfreader.mdfinfo4*), 39
- ## E
- EVBlock (class in *mdfreader.mdfinfo4*), 39
- export_to_csv() (*mdfreader.mdfreader.Mdf* method), 4, 6
- export_to_excel() (*mdfreader.mdfreader.Mdf* method), 4, 7
- export_to_hdf5() (*mdfreader.mdfreader.Mdf* method), 4, 7
- export_to_matlab() (*mdfreader.mdfreader.Mdf* method), 4, 7

`export_to_NetCDF()` (*mdfreader.mdfreader.Mdf method*), 4, 6
`export_to_parquet()` (*mdfreader.mdfreader.Mdf method*), 7
`export_to_xlsx()` (*mdfreader.mdfreader.Mdf method*), 4, 8

F

`FHBlock` (*class in mdfreader.mdfinfo4*), 39
`fid` (*mdfreader.mdf.MdfSkeleton attribute*), 14
`fid` (*mdfreader.mdf3reader.DATA attribute*), 19
`fid` (*mdfreader.mdf4reader.Data attribute*), 27
`fid` (*mdfreader.mdfinfo3.Info3 attribute*), 25
`fid` (*mdfreader.mdfinfo4.Info4 attribute*), 40
`fid` (*mdfreader.mdfreader.MdfInfo attribute*), 11
`file_name` (*mdfreader.mdfinfo3.Info3 attribute*), 25
`fileMetadata` (*mdfreader.mdf.MdfSkeleton attribute*), 14
`fileMetadata` (*mdfreader.mdf3reader.Mdf3 attribute*), 21
`fileMetadata` (*mdfreader.mdf4reader.Mdf4 attribute*), 29
`fileMetadata` (*mdfreader.mdfreader.Mdf attribute*), 4
`fileName` (*mdfreader.mdf.MdfSkeleton attribute*), 14
`fileName` (*mdfreader.mdf3reader.Mdf3 attribute*), 20
`fileName` (*mdfreader.mdf4reader.Mdf4 attribute*), 28
`fileName` (*mdfreader.mdfinfo3.Info3 attribute*), 25
`fileName` (*mdfreader.mdfinfo4.Info4 attribute*), 40
`fileName` (*mdfreader.mdfreader.Mdf attribute*), 3
`fileName` (*mdfreader.mdfreader.MdfInfo attribute*), 11
`filterChannelNames` (*mdfreader.mdf.MdfSkeleton attribute*), 14
`filterChannelNames` (*mdfreader.mdf3reader.Mdf3 attribute*), 20
`filterChannelNames` (*mdfreader.mdf4reader.Mdf4 attribute*), 29
`filterChannelNames` (*mdfreader.mdfinfo3.Info3 attribute*), 25
`filterChannelNames` (*mdfreader.mdfinfo4.Info4 attribute*), 40
`filterChannelNames` (*mdfreader.mdfreader.MdfInfo attribute*), 11
`Flags` (*mdfreader.mdf4reader.Record attribute*), 30

G

`generate_chunks()` (*mdfreader.mdf4reader.Record method*), 31
`get_channel()` (*mdfreader.mdf.MdfSkeleton method*), 15
`get_channel_conversion()` (*mdfreader.mdf.MdfSkeleton method*), 15
`get_channel_data()` (*mdfreader.mdfreader.Mdf method*), 4, 8

`get_channel_desc()` (*mdfreader.mdf.MdfSkeleton method*), 15
`get_channel_master()` (*mdfreader.mdf.MdfSkeleton method*), 15
`get_channel_master_type()` (*mdfreader.mdf.MdfSkeleton method*), 15
`get_channel_name4()` (*mdfreader.mdf4reader.Mdf4 method*), 29
`get_channel_name_4()` (*mdfreader.mdf4reader.Mdf4 method*), 29
`get_channel_unit()` (*mdfreader.mdf.MdfSkeleton method*), 15
`get_channel_unit()` (*mdfreader.mdfreader.Mdf method*), 4
`get_invalid_bit()` (*mdfreader.mdf.MdfSkeleton method*), 15
`get_invalid_channel()` (*mdfreader.mdf.MdfSkeleton method*), 15
`get_invalid_mask()` (*mdfreader.mdf4reader.Mdf4 method*), 29

H

`has_invalid_bit()` (*mdfreader.channel.Channel4 method*), 49
`HDBlock` (*class in mdfreader.mdfinfo4*), 39
`hiddenBytes` (*mdfreader.mdf3reader.Record attribute*), 23
`hiddenBytes` (*mdfreader.mdf4reader.Record attribute*), 31
`HLBlock` (*class in mdfreader.mdfinfo4*), 39

I

`IDBlock` (*class in mdfreader.mdfinfo4*), 39
`info` (*mdfreader.mdf.MdfSkeleton attribute*), 15
`Info3` (*class in mdfreader.mdfinfo3*), 25
`Info4` (*class in mdfreader.mdfinfo4*), 40
`initialise_reccarray()` (*mdfreader.mdf4reader.Record method*), 31
`invalid_bit()` (*mdfreader.channel.Channel4 method*), 49
`invalid_channel` (*mdfreader.mdf4reader.Record attribute*), 31
`is_ca_block()` (*mdfreader.channel.Channel4 method*), 50
`isnumeric()` (*mdfreader.channel.Channel4 method*), 50

K

`keep_channels()` (*mdfreader.mdfreader.Mdf method*), 5, 8

L

`LDBlock` (*class in mdfreader.mdfinfo4*), 42

- `list_channels()` (`mdfreader.mdfreader.MdfInfo` method), 11
 - `list_channels3()` (`mdfreader.mdfinfo3.Info3` method), 25
 - `list_channels4()` (`mdfreader.mdfinfo4.Info4` method), 40
 - `little_endian()` (`mdfreader.channel.Channel4` method), 50
 - `load()` (`mdfreader.mdf4reader.Data` method), 27
 - `load()` (`mdfreader.mdfinfo4.CABlock` method), 35
 - `load()` (`mdfreader.mdfinfo4.CommentBlock` method), 36
 - `load()` (`mdfreader.mdfinfo4.DIBlock` method), 38
 - `load()` (`mdfreader.mdfinfo4.DTBlock` method), 38
 - `load()` (`mdfreader.mdfinfo4.DVBlock` method), 38
 - `load()` (`mdfreader.mdfinfo4.HLBlock` method), 39
 - `load()` (`mdfreader.mdfinfo4.LDBlock` method), 42
 - `load_info()` (`mdfreader.mdf3reader.Record` method), 23
 - `load_info()` (`mdfreader.mdf4reader.Record` method), 31
 - `load_sorted()` (`mdfreader.mdf3reader.DATA` method), 19
 - `load_unsorted()` (`mdfreader.mdf3reader.DATA` method), 19, 20
 - `loadInfo()` (`mdfreader.mdf3reader.Record` method), 23
- ## M
- `master` (`mdfreader.mdf3reader.Record` attribute), 22
 - `master` (`mdfreader.mdf4reader.Record` attribute), 31
 - `masterChannelList` (`mdfreader.mdf.MdfSkeleton` attribute), 15
 - `masterChannelList` (`mdfreader.mdf3reader.Mdf3` attribute), 20
 - `masterChannelList` (`mdfreader.mdf4reader.Mdf4` attribute), 28
 - `masterChannelList` (`mdfreader.mdfreader.Mdf` attribute), 4
 - `Mdf` (class in `mdfreader.mdfreader`), 3
 - `Mdf3` (class in `mdfreader.mdf3reader`), 20
 - `Mdf4` (class in `mdfreader.mdf4reader`), 28
 - `MdfInfo` (class in `mdfreader.mdfreader`), 10
 - `mdfreader.channel` (module), 45
 - `mdfreader.mdf` (module), 13
 - `mdfreader.mdf3reader` (module), 19
 - `mdfreader.mdf4reader` (module), 27
 - `mdfreader.mdfinfo3` (module), 25
 - `mdfreader.mdfinfo4` (module), 35
 - `mdfreader.mdfreader` (module), 3
 - `MdfSkeleton` (class in `mdfreader.mdf`), 13
 - `mdfversion` (`mdfreader.mdfreader.MdfInfo` attribute), 11
 - `MDFVersionNumber` (`mdfreader.mdf.MdfSkeleton` attribute), 13
 - `MDFVersionNumber` (`mdfreader.mdf3reader.Mdf3` attribute), 20
 - `MDFVersionNumber` (`mdfreader.mdf4reader.Mdf4` attribute), 28
 - `MDFVersionNumber` (`mdfreader.mdfreader.Mdf` attribute), 4
 - `merge_mdf()` (`mdfreader.mdfreader.Mdf` method), 8
 - `MLSD` (`mdfreader.mdf4reader.Record` attribute), 30
 - `multiProc` (`mdfreader.mdf.MdfSkeleton` attribute), 15
 - `multiProc` (`mdfreader.mdf3reader.Mdf3` attribute), 20
 - `multiProc` (`mdfreader.mdf4reader.Mdf4` attribute), 28
 - `multiProc` (`mdfreader.mdfreader.Mdf` attribute), 4
- ## N
- `name` (`mdfreader.channel.Channel3` attribute), 45
 - `name` (`mdfreader.channel.Channel4` attribute), 50
 - `native_data_format()` (`mdfreader.channel.Channel4` method), 50
 - `nBytes_aligned` (`mdfreader.channel.Channel3` attribute), 46
 - `nBytes_aligned` (`mdfreader.channel.Channel4` attribute), 50
 - `numberOfRecords` (`mdfreader.mdf3reader.Record` attribute), 22
 - `numberOfRecords` (`mdfreader.mdf4reader.Record` attribute), 31
 - `numpy_format()` (`mdfreader.channel.Channel4` method), 50
 - `numpyDataRecordFormat` (`mdfreader.mdf3reader.Record` attribute), 22
 - `numpyDataRecordFormat` (`mdfreader.mdf4reader.Record` attribute), 31
- ## P
- `plot()` (`mdfreader.mdfreader.Mdf` method), 4, 8
 - `plot_all()` (`mdfreader.mdfreader.Mdf` method), 8
 - `pointer_to_data` (`mdfreader.mdf4reader.Data` attribute), 28
 - `pointerToData` (`mdfreader.mdf3reader.DATA` attribute), 19
 - `pos_bit_beg` (`mdfreader.channel.Channel4` attribute), 50
 - `pos_bit_begin()` (`mdfreader.channel.Channel4` method), 50
 - `pos_bit_end()` (`mdfreader.channel.Channel4` method), 50
 - `pos_byte_beg()` (`mdfreader.channel.Channel4` method), 50
 - `pos_byte_end()` (`mdfreader.channel.Channel4` method), 50
 - `posByteBeg` (`mdfreader.channel.Channel3` attribute), 46

`posByteEnd` (*mdfreader.channel.Channel3* attribute), 46
`PythonVersion` (in module *mdfreader.channel*), 45

R

`read()` (*mdfreader.mdf3reader.DATA* method), 19, 20
`read()` (*mdfreader.mdf4reader.Data* method), 28
`read()` (*mdfreader.mdfinfo4.CABlock* method), 35
`read()` (*mdfreader.mdfinfo4.FHBlock* method), 39
`read()` (*mdfreader.mdfinfo4.HDBlock* method), 39
`read()` (*mdfreader.mdfinfo4.IDBlock* method), 39
`read()` (*mdfreader.mdfreader.Mdf* method), 8
`read3()` (*mdfreader.mdf3reader.Mdf3* method), 21
`read4()` (*mdfreader.mdf4reader.Mdf4* method), 29
`read_all_channels_sorted_record()` (*mdfreader.mdf4reader.Record* method), 31
`read_cc()` (*mdfreader.mdfinfo4.CCBlock* method), 35
`read_cc_block()` (in module *mdfreader.mdfinfo3*), 26
`read_ce_block()` (in module *mdfreader.mdfinfo3*), 26
`read_cg()` (*mdfreader.mdfinfo4.CGBlock* method), 35
`read_cg_block()` (in module *mdfreader.mdfinfo3*), 26
`read_cg_block()` (*mdfreader.mdfinfo3.Info3* method), 25
`read_cg_block()` (*mdfreader.mdfinfo4.Info4* method), 40
`read_cg_blocks()` (*mdfreader.mdfinfo4.Info4* method), 40
`read_ch_block()` (*mdfreader.mdfinfo4.Info4* method), 41
`read_channels_from_bytes()` (*mdfreader.mdf4reader.Record* method), 32
`read_channels_from_bytes_fallback()` (*mdfreader.mdf4reader.Record* method), 32
`read_cm_at()` (*mdfreader.mdfinfo4.CommentBlock* method), 36
`read_cm_cc()` (*mdfreader.mdfinfo4.CommentBlock* method), 36
`read_cm_cc_unit()` (*mdfreader.mdfinfo4.CommentBlock* method), 36
`read_cm_cg()` (*mdfreader.mdfinfo4.CommentBlock* method), 36
`read_cm_ch()` (*mdfreader.mdfinfo4.CommentBlock* method), 36
`read_cm_cn()` (*mdfreader.mdfinfo4.CommentBlock* method), 36
`read_cm_cn_unit()` (*mdfreader.mdfinfo4.CommentBlock* method), 36
`read_cm_dg()` (*mdfreader.mdfinfo4.CommentBlock* method), 37
`read_cm_ev()` (*mdfreader.mdfinfo4.CommentBlock* method), 37
`read_cm_fh()` (*mdfreader.mdfinfo4.CommentBlock* method), 37
`read_cm_hd()` (*mdfreader.mdfinfo4.CommentBlock* method), 37
`read_cm_header()` (*mdfreader.mdfinfo4.CommentBlock* method), 37
`read_cm_si()` (*mdfreader.mdfinfo4.CommentBlock* method), 37
`read_cn()` (*mdfreader.mdfinfo4.CNBlock* method), 35
`read_cn_block()` (in module *mdfreader.mdfinfo3*), 26
`read_cn_block()` (*mdfreader.mdfinfo4.Info4* method), 41
`read_cn_blocks()` (*mdfreader.mdfinfo4.Info4* method), 41
`read_data_list()` (*mdfreader.mdf4reader.Data* method), 28
`read_dg()` (*mdfreader.mdfinfo4.DGBlock* method), 38
`read_dg_block()` (in module *mdfreader.mdfinfo3*), 26
`read_dg_block()` (*mdfreader.mdfinfo4.Info4* method), 41
`read_dl()` (*mdfreader.mdfinfo4.DLBlock* method), 38
`read_dz()` (*mdfreader.mdfinfo4.DZBlock* method), 39
`read_ev_block()` (*mdfreader.mdfinfo4.Info4* static method), 42
`read_hd_block()` (in module *mdfreader.mdfinfo3*), 26
`read_hl()` (*mdfreader.mdfinfo4.HLBlock* method), 39
`read_info()` (*mdfreader.mdfinfo4.Info4* method), 42
`read_info()` (*mdfreader.mdfreader.MdfInfo* method), 11
`read_info3()` (*mdfreader.mdfinfo3.Info3* method), 26
`read_ld()` (*mdfreader.mdfinfo4.LDBlock* method), 42
`read_not_all_channels_sorted_record()` (*mdfreader.mdf4reader.Record* method), 32
`read_record()` (*mdfreader.mdf4reader.Data* method), 28
`read_record_bits()` (*mdfreader.mdf3reader.Record* method), 23
`read_record_buf()` (*mdfreader.mdf3reader.Record* method), 23
`read_record_buf()` (*mdfreader.mdf4reader.Record* method), 32
`read_si()` (*mdfreader.mdfinfo4.SIBlock* method), 43
`read_sorted_record()` (*mdfreader.mdf3reader.Record* method), 23
`read_sorted_record()` (*mdfreader.mdf4reader.Record* method), 33
`read_sr_block()` (*mdfreader.mdfinfo4.Info4* static method), 42

`read_tx()` (*mdfreader.mdfinfo4.CommentBlock method*), 37
`read_tx_block()` (*in module mdfreader.mdfinfo3*), 26
`read_unique_channel()` (*mdfreader.mdf4reader.Record method*), 33
`read_xml()` (*mdfreader.mdfinfo4.CommentBlock method*), 37
`readRecordBits()` (*mdfreader.mdf3reader.Record method*), 23
`readRecordBuf()` (*mdfreader.mdf3reader.Record method*), 23
`readSortedRecord()` (*mdfreader.mdf3reader.Record method*), 23
`recAttributeName` (*mdfreader.channel.Channel3 attribute*), 46
`Record` (*class in mdfreader.mdf3reader*), 22
`Record` (*class in mdfreader.mdf4reader*), 30
`record_attribute_name()` (*mdfreader.channel.Channel4 method*), 51
`record_id_size()` (*mdfreader.channel.Channel4 method*), 51
`RecordFormat` (*mdfreader.channel.Channel3 attribute*), 46
`recordID` (*mdfreader.mdf3reader.Record attribute*), 22
`recordID` (*mdfreader.mdf4reader.Record attribute*), 33
`recordIDCFormat` (*mdfreader.mdf4reader.Record attribute*), 33
`recordIDnumber` (*mdfreader.mdf3reader.Record attribute*), 22
`recordIDsize` (*mdfreader.mdf4reader.Record attribute*), 33
`recordLength` (*mdfreader.mdf3reader.Record attribute*), 22
`recordLength` (*mdfreader.mdf4reader.Record attribute*), 33
`recordToChannelMatching` (*mdfreader.mdf3reader.Record attribute*), 22
`recordToChannelMatching` (*mdfreader.mdf4reader.Record attribute*), 33
`remove_channel()` (*mdfreader.mdf.MdfSkeleton method*), 15
`remove_channel_conversion()` (*mdfreader.mdf.MdfSkeleton method*), 16
`rename_channel()` (*mdfreader.mdf.MdfSkeleton method*), 16
`resample()` (*mdfreader.mdfreader.Mdf method*), 4, 9
`resample_group()` (*mdfreader.mdfreader.Mdf method*), 10
`return_pandas_dataframe()` (*mdfreader.mdfreader.Mdf method*), 10
S
`set()` (*mdfreader.channel.Channel4 method*), 51
`set_CANOpen()` (*mdfreader.channel.Channel4 method*), 51
`set_channel_attachment()` (*mdfreader.mdf.MdfSkeleton method*), 16
`set_channel_conversion()` (*mdfreader.mdf.MdfSkeleton method*), 16
`set_channel_data()` (*mdfreader.mdf.MdfSkeleton method*), 16
`set_channel_desc()` (*mdfreader.mdf.MdfSkeleton method*), 16
`set_channel_master()` (*mdfreader.mdf.MdfSkeleton method*), 16
`set_channel_master_type()` (*mdfreader.mdf.MdfSkeleton method*), 17
`set_channel_unit()` (*mdfreader.mdf.MdfSkeleton method*), 17
`set_invalid_bit()` (*mdfreader.mdf.MdfSkeleton method*), 17
`set_invalid_bytes()` (*mdfreader.channel.Channel4 method*), 51
`set_invalid_channel()` (*mdfreader.mdf.MdfSkeleton method*), 17
`SIBlock` (*class in mdfreader.mdfinfo4*), 43
`signal_data_type()` (*mdfreader.channel.Channel4 method*), 51
`signalDataType` (*mdfreader.channel.Channel3 attribute*), 45
`SRBlock` (*class in mdfreader.mdfinfo4*), 43
T
`type` (*mdfreader.channel.Channel4 attribute*), 52
`type` (*mdfreader.mdf4reader.Data attribute*), 28
U
`unique_channel_in_DG` (*mdfreader.mdf4reader.Record attribute*), 33
`unique_id()` (*mdfreader.mdfinfo4.Info4 method*), 42
`unit` (*mdfreader.channel.Channel3 attribute*), 45
`unit()` (*mdfreader.channel.Channel4 method*), 52
V
`VLSD` (*mdfreader.mdf4reader.Record attribute*), 30
`VLSD_CG` (*mdfreader.mdf4reader.Record attribute*), 30
`VLSD_CG_Flag` (*mdfreader.channel.Channel4 attribute*), 47
W
`write()` (*mdfreader.mdfinfo4.CABlock method*), 35
`write()` (*mdfreader.mdfinfo4.CGBlock method*), 35
`write()` (*mdfreader.mdfinfo4.CNBlock method*), 36
`write()` (*mdfreader.mdfinfo4.CommentBlock method*), 38
`write()` (*mdfreader.mdfinfo4.DGBlock method*), 38

[write\(\) \(mdfreader.mdfinfo4.DIBlock method\), 38](#)
[write\(\) \(mdfreader.mdfinfo4.DLBlock method\), 38](#)
[write\(\) \(mdfreader.mdfinfo4.DTBlock method\), 38](#)
[write\(\) \(mdfreader.mdfinfo4.DVBlock method\), 38](#)
[write\(\) \(mdfreader.mdfinfo4.DZBlock method\), 39](#)
[write\(\) \(mdfreader.mdfinfo4.FHBlock method\), 39](#)
[write\(\) \(mdfreader.mdfinfo4.HDBlock method\), 39](#)
[write\(\) \(mdfreader.mdfinfo4.HLBlock method\), 39](#)
[write\(\) \(mdfreader.mdfinfo4.IDBlock method\), 39](#)
[write\(\) \(mdfreader.mdfinfo4.LDBlock method\), 42](#)
[write\(\) \(mdfreader.mdfreader.Mdf method\), 4, 10](#)
[write3\(\) \(mdfreader.mdf3reader.Mdf3 method\), 21](#)
[write4\(\) \(mdfreader.mdf4reader.Mdf4 method\), 29, 30](#)
[write_DIV\(\) \(mdfreader.mdfinfo4.LDBlock method\), 42](#)
[write_DZ\(\) \(mdfreader.mdfinfo4.LDBlock method\), 43](#)

Z

[zipfile \(mdfreader.mdf.MdfSkeleton attribute\), 17](#)
[zipfile \(mdfreader.mdfinfo4.Info4 attribute\), 42](#)
[zipfile \(mdfreader.mdfreader.MdfInfo attribute\), 11](#)